


# Setting up Silomail on Mozilla Thunderbird

Upon launching Thunderbird for the first time a window will pop up asking you for information about your e-mail address.

1. Input your information as seen below, once done click **Continue**.



Mail Account Setup

Your name: John Doe Your name, as shown to others


Email address: johndoe@silomail.com

Password: ●●●●●

Remember password

Cancel Continue

2. When you see the below screen, click **stop**.



Mail Account Setup

Your name: John Doe Your name, as shown to others

Email address: johndoe@silomail.com

Password: ●●●●●

Remember password [Start over](#)


**Thunderbird is looking up the settings for your email account.**

Username: johndoe

● Incoming:	imap.silomail.com	IMAP	143	STARTTLS
⚙ Outgoing:	smtp.silomail.com	SMTP	587	STARTTLS

# Setting up Silomail on Mozilla Thunderbird


3. Change the incoming and outgoing server information under **Editing Config** to match the below picture. Once done, click **Manual Setup**.



The screenshot shows the 'Mail Account Setup' dialog box. It contains the following fields and options:

- Your name:** John Doe (Your name, as shown to others)
- Email address:** johndoe@silomail.com
- Password:** [Redacted]
- Remember password
- [Start over](#)
- Editing Config**
  - Username:** johndoe (with [Re-test Configuration](#) button)
  - Incoming:** pop3.silomail.com (with POP dropdown, 110, and None dropdown)
  - Outgoing:** smtp.silomail.com (with SMTP dropdown, 25, and None dropdown)
- [Manual Setup...](#)
- [Cancel](#)
- [Create Account](#)

4. Once the **Account Settings** window pops up, click on **Outgoing Server (SMTP)** and click **Edit**.



The screenshot shows the 'Account Settings' dialog box. The left sidebar shows the account 'johndoe@silomail.com' with various settings categories. The 'Outgoing Server (SMTP)' category is selected. The main area displays the 'Outgoing Server (SMTP) Settings' for the default server:


- Outgoing Server (SMTP) Settings**
- Although you can specify more than one outgoing server (SMTP), this is only recommended for advanced users. Setting up multiple SMTP servers can cause errors when sending messages.
- Server Name: smtp.silomail.com
- Port: 25
- User Name: johndoe
- Secure Authentication: No
- Connection Security: None

Buttons for 'Add...', 'Edit...', 'Remove', and 'Set Default' are visible. At the bottom, there are 'Account Actions' and 'OK'/'Cancel' buttons.

# Setting up Silomail on Mozilla Thunderbird

5. Once the **SMTP Server** window opens, click the box next to **Use name and password**, then input the first part of your e-mail address (leaving off *@silomail.com*) in the **User Name** field, then click **OK**.

**Note:** This may have already been completed automatically, if you open the **SMTP Server** settings box and find these setting already there, click **OK** to close the box.



6. Compose an e-mail, address it to [test@silomail.com](mailto:test@silomail.com) and click send. If the below box pops up, enter your e-mail password, check the box next to **Use Password Manager to remember this password**, and click **OK**.



**Congratulations!** Your set up is complete!

If everything has been set up properly you will soon receive a reply to your test e-mail confirming it was sent successfully.